| MIDI Controller List MultiVoicer (9.7.3.5)    | MIDI CC                |
|---|------------------------|
| [ Main ] multiVoicer (Globals)                |                        |
| Total Reset                                   | 111                    |
| All Notes Off                                 | 123                    |
| Start/Processing MultiVoicer                  | 110 (data2 > 63)       |
| MultiTimbral/Solo Mode                        | 109                    |
| apply Note Grid (On/Off)                      | 108                    |
| View Note Grid (On/Off)                       | 107                    |
| Select MIDI Channel to VIEW                   | 22                     |
| Change Chord if Vel. IN                       | 23                     |
| Small Vel. Variation per Voice (On/Off)       | 106                    |
| View dN (On/Off)                              | 105                    |
| File Speed Buttons (19)                       | 24 (values 10, 20, 90) |
| All same Chord Method (On/Off)                | 104                    |
| All same Chord (On/Off)                       | 103                    |
| Sequential MIDI In Active (On/Off)            | 102                    |
| Seq. MIDI Channel IN                          | 25                     |
| Select Chord Presets (active MIDI In Channel) | 26 (data2 = 11,,32)    |
| Init Chords                                   | 45                     |
| [ Main ] multiVoicer (per Channel)            |                        |
| Chord Method                                  | 27 (Values 1132)       |
| Range IN Low                                  | 28                     |
| Range IN High                                 | 29                     |
| Range IN Active (On/Off)                      | 101                    |
| Range OUT Low                                 | 30                     |
| Range OUT High                                | 31                     |
| Range OUT Active (On/Off)                     | 100                    |
| Note GATED (On/Off)                           | 99                     |
| Thru (On/Off)                                 | 98                     |
| Time GATED (On/Off)                           | 97                     |
| Gate Time (259999)                            | 32                     |
| Voice Choice (Bass / Top / in Between)        | 33                     |
| PlayVoice if Vel. In < Fader                  | 34 (value 0 31)        |
| Velocity Scaling                              | 34 (value 32 95)       |
| PlayVoice if Vel. In > Fader                  | 34 (value 96 127)      |
| Volume Mapping Offset                         | 35                     |
| Volume Mapping Curve (from Offset to 127)     | 36                     |

| MIDI Controller List MultiVoicer (9.7.3.5)     | MIDI CC                             |
|--|-------------------------------------|
| Active Vel. Faders Down, Up (-5,-3,-1,0,1,3,5) | 71 (Values 16,32,48,64=0,80,96,112) |
|  |                                     |
| [ Main ] multiVoicer (per Chan. & per Voice)   |                                     |
| Voice Active (19)                              | 9688                                |
| Voice Interval                                 | 3744                                |
| Voice Velocity Fader                           | 4654                                |
| Voice Output Channel                           | 5563                                |
|  |                                     |
|  |                                     |
|  |                                     |
| [ dN ] Module                                  |                                     |
| Major Presets (-5, -4, 0, 1, 2, 6)             | 65                                  |
| Memory Presets (S1-S6)                         | 66                                  |
| Reset dN                                       | 87                                  |
| [ aN ] Module                                  |                                     |
| Reset aN                                       | 86                                  |
| Select All MIDI Channels                       | 85                                  |
| Make Note Grid Table                           | 84                                  |
| Select a PRESET SCALE                          | 67                                  |
| Select the Start Key Note                      | 68                                  |
| Scale Chords for NON-Scale Input Note to       | 69                                  |
| Scale Length (012)                             | 70                                  |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |
|  |                                     |